

How to Update ScanStation Pxx

- when it has to be **right**




1. Ensure sufficient power supply for ScanStation Pxx (for at least 40 minutes).
2. Copy the firmware upgrade package (file with extension *.fw) to the root directory of a USB drive.
3. Switch on ScanStation Pxx.
4. Wait for the **Main Menu** to appear on the touch screen.
5. Connect the USB drive to ScanStation Pxx and wait for the external hard drive icon  to appear in the status bar.
6. Click **Tools**.




→ The **Tools Menu** is displayed.

7. Click **Transfer**.




→ The **Transfer Menu** is displayed.


8. Click **System Files**.




- The **Transfer System Files** panel is displayed.
9. Select the appropriate FW file from the drop-down list of the **Firmware** field.
 10. Press **Cont.**




- A confirmation box appears asking whether you really want to upgrade.
11. Press **Yes**



- Another confirmation box appears asking for sufficient power supply during the upgrade process
12. Check the power supply and press **Yes**.



- The FW file is copied from the USB drive onto the ScanStation Pxx. A message box appears afterwards asking to remove the USB drive.
13. Remove the USB drive.
 14. Press **OK**.



- The upgrade process will start. It may take up to 30 minutes. After the upgrade process the ScanStation Pxx will restart. Then the **Main Menu** will come up again.